

Assembly Monitoring System

Complete Line-by-Line Code Walkthrough

Every line explained for absolute beginners

How to Use This Guide

This document explains **every single line** of the assembly monitoring code. Red text shows the actual code, green text explains what it does. Even with zero programming experience, you'll understand this system by the end.

The system uses AI (YOLO) to watch a video camera and detect when assembly workers install parts. It checks that parts are installed in the correct order and displays progress on a web page.

SECTION 1: IMPORTING LIBRARIES (Lines 1-20)

These lines load external tools (libraries) that the program needs. Think of them as importing tools into a workshop - you can't build without your tools!

```
import time
```

What: Loads Python's time library

Why: Handles anything time-related - delays, timestamps, measuring duration

Example use: Measuring how long the assembly takes, ensuring 30-second wait after pin installation

```
import sys
```

What: Loads system library

Why: Access system functions, modify Python's import paths

In this code: Partially used (has commented code for path modification)

```
from uuid import uuid4
```

What: Imports the uuid4 function

Why: Generates unique random IDs

Example use: Creates unique filename for each recording: 'a7b2c8-1234-5678.mp4'

```
import queue
```

What: Loads queue data structure

Why: Thread-safe way to pass data between parts of program running simultaneously

Analogy: Like a line at a store - first in, first out

```
import threading
```

What: Loads Python's threading library

Why: Run multiple tasks simultaneously

Example: One thread captures video, another processes frames - both run at same time

```
import cv2
```

What: Loads OpenCV (cv2 = Computer Vision 2)

Why: THE main library for working with images and video

Can do: Read videos, draw shapes, add text, resize images, etc.

```
from skimage.metrics import structural_similarity as ssim
```

What: Imports SSIM function from scikit-image

Why: Compares how similar two images are (1.0=identical, 0.0=different)

Note: Imported but not actively used in current version

```
import av
```

What: Loads PyAV (Python + FFmpeg)

Why: Faster video processing than OpenCV, supports GPU acceleration

Usage: Reads RTSP camera stream efficiently

```
import math
```

What: Loads math functions

Why: Provides sqrt, sin, cos, and importantly math.dist()

Usage: Calculates distance between two hand positions

```
from collections import deque
```

What: Imports deque (double-ended queue)

Why: Special list with max size - automatically removes oldest when full

Example: deque(maxlen=30) keeps only last 30 detections

```
from flask import Flask, Response, request, url_for
```

What: Imports Flask web framework components

Why: Turns Python program into a web server

Components: Flask(app), Response(custom responses), request(incoming data), url_for(URLs)

```
import os
```

What: Operating system interface

Why: File operations, environment variables

Usage: Sets OpenCV logging levels via environment variables

```
import numpy as np
```

What: NumPy - numerical computing library

Why: Images ARE numpy arrays! A 1920×1080 image = array[1080, 1920, 3]

Essential for: All image/video processing

```
from ultralytics import YOLO
import ultralytics
```

What: Imports YOLO AI framework

Why: The 'brain' that detects objects in images

Trained to recognize: Assembly parts, tools, hand positions

```
ultralytics.checks()
```

What: Runs YOLO system check

Why: Verifies PyTorch, CUDA, dependencies are installed

Prints: System report showing what's available

SECTION 2: OPENCV CONFIGURATION (Lines 18-23)

```
try:  
cv2.utils.logging.setLogLevel(cv2.utils.logging.LOG_LEVEL_ERROR)
```

What: Try to silence OpenCV warnings (modern version)

try block: Attempts code that might fail

Why: OpenCV prints LOTS of messages - we only want errors

```
except Exception:  
os.environ['OPENCV_LOG_LEVEL'] = 'ERROR'  
os.environ['OPENCV_FFMPEG_CAPTURE_OPTIONS'] = 'rtsp_transport;tcp'
```

What: If try failed, use environment variables (older OpenCV)

except Exception: Catches any error from try block

OPENCV_LOG_LEVEL: Only show errors

OPENCV_FFMPEG_CAPTURE_OPTIONS: Use TCP for RTSP (more reliable than UDP)

SECTION 3: LOADING AI MODELS (Lines 25-31)

```
pos_model = YOLO('models/yolov8n-pose.pt', task='pose',)
```

What: Load pose detection AI model

pos_model = Variable to store the model

'models/yolov8n-pose.pt': File containing trained weights

task='pose': Detects human body positions/keypoints

Detects: Hand positions, elbows, shoulders for tracking worker movements

```
pos_model.predict('defect_scanner_logo.png', conf=0.4, iou=0.8, imgsz=640, verbose=False, device=[0])
```

What: Warm-up prediction (makes future predictions faster)

'defect_scanner_logo.png': Dummy image (doesn't matter what)

conf=0.4: Confidence threshold - only show detections >40% confident

iou=0.8: Intersection-over-Union for overlapping detections

imgsz=640: Resize to 640×640 for processing

verbose=False: Don't print details

device=[0]: Use first GPU

Why warm-up: First prediction loads model into GPU memory (slow). Next predictions fast!

```
tower_model = YOLO('models/AL_tower_271225.pt', task='detect')
```

What: Load custom object detection model

'AL_tower_271225.pt': Custom model trained Dec 27, 2025

task='detect': Object detection (finding and labeling parts)

Trained on: End covers, bolts, clamps, hammers, drills, hands - all assembly components

```
print(tower_model.names)
```

What: Prints object class names

Outputs: {0: 'end_cover', 1: 'end_cover_bolt', 2: 'tower', ...}

Why useful: Confirms model loaded correctly, shows what it can detect

SECTION 4: GLOBAL VARIABLES (Lines 33-65)

```
all_steps = ['End cover fitment', 'End cover bolt fitment', 'Clamping', ...]
```

What: List of all 16 assembly step names

Why list: Each step has index 0-15

Usage: When step 5 completes, look up all_steps[5] = 'Circlip fitment'

Full list: 0-End cover, 1-Bolt, 2-Clamp, 3-Interlock pin, 4-Hammering, 5-Circlip, 6-Lock circlip, 7-Drain plug, 8-Loctite, 9-Cutoff valve, 10/11/12-Tightening, 13-Detent plunger, 14-Yellow spring, 15-Pink spring

```
cycle_check = []
```

```
cycle_check_time = []
```

What: Empty lists to track progress

cycle_check: Stores completed step numbers [0, 1, 2, 3]

cycle_check_time: Would store timestamps (not used currently)

Why empty: No steps completed when program starts

```
loc = threading.Lock()
```

What: Creates a thread lock

Why: Prevents multiple threads from accessing same data simultaneously

Analogy: Bathroom lock - only one person at a time

Usage: loc.acquire() = lock door, loc.release() = unlock door

```
dummy_img = cv2.imread('defect_scanner_logo.png')
```

```
logo = cv2.imread('defect-scanner-logo-transparent-cropped.png')
```

What: Load images from files

dummy_img: Placeholder shown before camera connects

logo: Logo overlaid on every frame (watermark)

cv2.imread(): Reads image file into numpy array

```
frame_ori = dummy_img.copy()
```

```
capFrame = dummy_img.copy()
```

What: Create copies of placeholder image

.copy(): Creates separate copy (not just reference)

frame_ori: Original frame before processing

capFrame: Current frame from camera (starts as placeholder)

```
rec_vid = False
```

```
video_rec = 0
```

What: Recording control variables

rec_vid: True=recording, False=not recording

video_rec: VideoWriter object (0=none, object=active recorder)

Toggle: Visit /record URL to switch between recording states

```
cycle_check_f = 0
```

What: Cycle status flag

Values: 0=in progress, 10=completed

Display: Shows 'In Progress' or 'Completed' status

```
cycle_start_time = None
```

What: When assembly cycle started

None: Python for 'no value yet'

Set to: time.time() when first step detected

Usage: Calculate elapsed time: time.time() - cycle_start_time

```
cls_ins = deque(maxlen=30)
```

```
tower_conf = deque(maxlen=20)
```

What: Deques for recent detection history

cls_ins: Last 30 object detections

tower_conf: Last 20 tower presence checks

Auto-remove: When 31st added, oldest drops off

Confirmation: Object must appear 3+ times in last 30 to be valid

```
sequence_break_f = 0
```

What: Sequence error tracker

Values: 0=no error, N=break at step N

Example: If circlip installed before hammering, sequence_break_f=5

Display: Shows blinking red warning when non-zero

```
detent_box_pos = [41, 232, 142, 309]
```

```
yellowS_box_pos = [216, 110, 279, 168]
```

```
pinkS_box_pos = [205, 187, 271, 238]
```

What: Screen regions for hand detection

Format: [x1, y1, x2, y2] = top-left to bottom-right

detent_box_pos: Where hands should be for detent plunger

yellowS_box_pos: Yellow spring installation area

pinkS_box_pos: Pink spring installation area

Check: if box[0] < hand_x < box[2] and box[1] < hand_y < box[3]: hand is inside!

```
hand_f = 0
```

```
spring_plungerf = 0
```

What: Hand detection flags

hand_f: Counter 0-3, increments when hand in position, decrements when not

spring_plungerf: 0=not verified, 1=installation confirmed

Verification: Both hands positioned correctly at proper distance

```
_, buffer = cv2.imencode('.jpg', dummy_img)
```

What: Encode image as JPEG

cv2.imencode(): Converts numpy array to JPEG bytes

Returns: (success_flag, jpeg_bytes)

_: Ignore success flag (underscore = don't care)

buffer: JPEG bytes ready to send to web browser

Why: Browsers can't display numpy arrays, need JPEG format

```
app = Flask(__name__,)
```

What: Create Flask web application

Flask(__name__): Initialize Flask app

__name__: Current module name

Enables: @app.route() decorators and app.run() server

Result: Python program becomes web server!

SECTION 5: CUSTOM THREAD CLASS (Lines 68-73)

```
class ThreadWithResult(threading.Thread):
```

What: Custom thread class that can return values

Why: Normal threads can't return values - this adds that feature

Inheritance: Extends threading.Thread with our additions

SECTION 6: FLASK ROUTES

Web endpoints users can visit

```
@app.route('/')
def index():
    return 'Ashok Leyland'
```

Root URL - just shows company name

```
@app.route('/clear')
def cls():
    cycle_check.clear()
    cycle_check_f = 0
```

Resets assembly progress - visit between units

```
@app.route('/record')
def record():
```

Toggles video recording on/off

SECTION 7: MAIN DETECTION LOGIC (frameInf function)

This is the 'brain' - processes each frame and detects assembly steps

Key Detection Rules:

- **Tower presence:** Must detect tower 3+ times before allowing any steps
- **End cover (0):** class 0 detected 3+ times
- **Bolt (1):** class 1 detected 3+ times AND step 0 complete
- **Clamp (2):** class 3 detected 3+ times
- **Interlock pin (3):** class 5 detected 3+ times, starts 30-second timer
- **Hammering (4):** class 4 (hammer) 2+ times AND must follow step 3
- **Circlip (5):** class 6 detected 3+ times AND 30 seconds after step 3
- **Lock circlip (6):** hammer after circlip
- **Drain plug (7):** class 7 detected 3+ times
- **Loctite (8):** class 8 detected 3+ times AND step 7 complete
- **Cutoff valve (9):** class 9 detected 3+ times
- **Tightening (10-12):** Drill position in specific coordinates
- **Springs (13-15):** Hand positions in specific boxes

SECTION 8: VIDEO CAPTURE (getF function)

```
video_path = 'rtsp://sourab:tvsm123!@192.168.0.101/stream1?tcp'
```

What: Camera URL

Format: rtsp://username:password@ip/stream

?tcp: Use TCP transport

Credentials: sourab / tvsm123!

```
container = av.open(video_path, options={'rtsp_transport': 'tcp', 'hwaccel': 'cuda'})
```

What: Open video stream with PyAV

rtsp_transport=tcp: Reliable connection

hwaccel=cuda: Use GPU to decode video (MUCH faster)

container: Video stream object

```
for frame in container.decode(video=0):  
    frame = frame.to_ndarray(format='bgr24')  
    frame = frame[450:1500, 550:2000]
```

What: Process each video frame

decode(video=0): Decode video stream

to_ndarray(): Convert to numpy array in BGR format

[450:1500, 550:2000]: Crop to region of interest (y:y, x:x)

Result: 1050×1450 pixel region focused on assembly area

SECTION 9: WEB STREAMING

```
def generate_frames():
    while True:
        res = frameInf(capFrame.copy())
        _, buffer = cv2.imencode('.jpg', res)
        yield (b'--frame\r\n' b'Content-Type: image/jpeg\r\n\r\n' + buffer.tobytes() + b'\r\n')
```

What: Generator function for MJPEG streaming

while True: Infinite loop

frameInf(): Process frame (add overlays, detect objects)

imencode(): Convert to JPEG

yield: Return frame and keep function alive

Multipart response: Each frame separated by --frame boundary

Result: Continuous stream of JPEG images = video!

```
@app.route('/video_feed')
def video_feed():
    return Response(generate_frames(), mimetype='multipart/x-mixed-replace; boundary=frame')
```

What: Endpoint that streams video

@app.route('/video_feed'): URL to visit

Response(): Custom HTTP response

generate_frames(): Generator function

mimetype: Tells browser this is MJPEG stream

Access: http://server-ip:5000/video_feed shows live video

SECTION 10: PROGRAM STARTUP

```
if __name__ == '__main__':  
    threading.Thread(target=getF, daemon=True).start()  
    app.run(host='0.0.0.0', port=5000)
```

What: Program entry point

if __name__ == '__main__': Only run if this is main file (not imported)

threading.Thread(target=getF): Create thread running getF function

daemon=True: Thread dies when main program exits

.start(): Start the thread (begins video capture)

app.run(): Start Flask web server

host='0.0.0.0': Listen on all network interfaces (accessible from other computers)

port=5000: Use port 5000

Result: Video capture runs in background, web server accepts connections

PROGRAM FLOW SUMMARY

Understanding the complete execution:

1. **Program starts** → Imports libraries, loads AI models
2. **Variables initialized** → All flags and lists set to defaults
3. **Video capture thread starts** → Connects to camera, continuously grabs frames
4. **Web server starts** → Flask listens on port 5000
5. **User visits /live** → Browser requests video stream
6. **For each frame:**
 - Capture frame from camera
 - Run YOLO detection on frame
 - Check which objects detected
 - Verify assembly sequence
 - Draw overlays (boxes, text, status)
 - Encode as JPEG
 - Send to browser
7. **Assembly progress tracked** → Steps added to cycle_check list
8. **User can:**
 - View live feed at /live
 - Toggle recording at /record
 - Reset progress at /clear
9. **Cycle completes** → All 16 steps detected in correct order
10. **Visit /clear** → Ready for next assembly unit

QUICK REFERENCE

Important URLs:

Live view: `http://[server-ip]:5000/live`

Video stream: `http://[server-ip]:5000/video_feed`

Clear progress: `http://[server-ip]:5000/clear`

Toggle recording: `http://[server-ip]:5000/record`

Color Codes:

Green: Step completed successfully

Yellow/Orange: Current step in progress

Red: Sequence break (wrong order)

White on blinking red: Step causing error

Key Variables to Remember:

cycle_check: List of completed steps [0,1,2,3...]

cls_ins: Last 30 detections (3+ needed to confirm)

sequence_break_f: 0=OK, N=error at step N

spring_plungerf: 1=spring installation verified

rec_vid: True=recording, False=not

End of Complete Code Walkthrough